
















Managing your Sessions

The session management panel shows a list of the sessions stored in your personal or team workspace.

Idera Test Sessions

MODE	NAME	TYPE	MODIFIED ↓	SIZE	OWNER	
	Jana 	 Session	Thu Nov 23 2023	4.95 kB	Joe	...
	Functionality check	 Session	Thu Nov 23 2023	3.96 kB	Joe	...
	Security concerns	 Session	Thu Nov 23 2023	3.47 kB	Joe	...
	Logging trials for Cross platform	 Session	Thu Nov 23 2023	3.91 kB	Joe	...
	Location and Language	 Session	Thu Nov 23 2023	13.1 kB	Joe	...
	Notifications	 Session	Thu Nov 23 2023		Joe	...
Showing 1-6 of 6						<div><div><</div><div>></div></div>

This panel displays the following information about each listed session or charter:

Item	Description
Mode	Every session has a connection mode which is identified by an icon: <div><div> Standalone session</div><div> Xray Jira connection session</div></div>
Name	The name of your session.
Type	The value for this field is Session.
Modified	Shows the latest modified date.
Size	The size of the session file.
Owner	The name of the user that created the session.
[...]	More options for each session or charter: <div><div><div>▪ Continue in desktop app</div><div>▪ Duplicate</div><div>▪ Download</div><div>▪ Rename</div><div>▪ Unlock</div><div>▪ Delete</div></div><div>Below, is more information about these options.</div></div>

More options [...]

The web console provides more options to manage your sessions. Below, find more details of the available options.

XRAY EXPLORATORY APP

Upgrade

B

Idera

Team Account

Idera Test Sessions

MODE

NAME

TYPE

MODIFIED ↓

SIZE

OWNER

Spectaculum

▷ Session

Sat Feb 24 2024105 GBBeatriz...

Necessitatibus

▷ Session

Sat Feb 24 202410.2 GBBeatriz...

Cuppedia Certus Calco Statua Curvo

▷ Session

Thu Feb 22 202414.3 GB...

Acies Coaegresco Compello Strenuus Caelestis

▷ Session

Sun Feb 18 2024121 GB...

Thesaurus Illum Valeo

▷ Session

Tue Feb 06 2024165 GB...

Showing 1-5 of 5

Continue in desktop app

Duplicate to

Download

Rename

Delete

Cloud Storage

16%

416 GB of 2.5 TB used

Get More Storage

Despite the role, users can duplicate sessions, download, rename, and delete the sessions they created.

Continue in desktop app

Select this option to open the session in the desktop app.

Duplicate to

Select this option to duplicate the session. Enter a name in the **Duplicate Test Session** dialog, select the workspace from the dropdown, and click **Duplicate** to complete the action.

Download

Select this option to download the session file.

Rename

Select this option to rename the session file.

Unlock

Select this option to unlock the session file. A session file becomes locked when a user opens it - this is because only one user is allowed to open the session at a time. The unlock option serves the purpose of unlocking one session file for the case that file stays in the locked state unexpectedly (e.g. user machine crashed and Xray Exploratory App was not able to unlock the file). Only the user than opens the session file, or an admin, can unlock a locked file session.

Delete

Select this option to delete the session file.

As a user, you can only delete the sessions you created. If you have Administrator privileges, you can delete any session.

Move

You can move a session file from one space to the other by creating a duplicated session in the target workspace (**Duplicate to**), and if you want you can delete the original session file from the first workspace (**Delete**).