

[Xray Server] Test Plan Board counters not correctly updated

When Test cases are moved simultaneously from the Orphans folder, the counters of the folders may become out of sync, and Test cases may be found in several folders.

Since the Test Plan Board only accepts the existence of one Test case per folder, this needs to be fixed.

Please execute the steps below to fix the counters and assure that only one Test case solely belongs to a folder.

Step-by-step guide

1. Please run this query on your instance database (please note that you may need to format the query to your Database syntax):

```
SELECT * FROM
  (SELECT TEST_ID,COUNT(*) AS COUNT from AO_8B1069_LEAF WHERE ENTITY_ID = 'Your_Test_Plan_issue_id' GROUP BY
  TEST_ID)
  AS COUNTS WHERE COUNTS.COUNT > 1
```

Make sure to replace **Your_Test_Plan_issue_id** in the query with the correct value.

You can find it by navigating to your Test Plan and hovering the mouse pointer over the **Edit** button. On the bottom of your browser, the preview URL will display the issue id value.

2. Take the TEST_ID column values and navigate to the JIRA Issue Search, and on Advanced run the following query:

```
id in (TEST_ID_1, TEST_ID_2, ...)
```

And create a Saved Filter **Duplicated Tests** with it.

3. Navigate to the Test Plan Board Folder where the problem occurred, use the **Filter**, and on the **Saved Filter** option input the previously created **Duplicated Tests**, and Apply.
4. Change the view to the **Folder view**.
5. Now, all the **tests** that appear are repeated at least one time; please take note of the issue key of each Test if you have **tests** inside the **Orphans** folder.
6. Select all the Tests, right-click on the selected **tests** and choose the option **Move to Orphans**.
7. Now, you have all the **tests** inside the **Orphans** folder, select all the **tests** from the **Orphans** folder or the **tests** that you take note and move to the original folder.

Related articles

- [\[Xray Server\] No permissions to execute Test Executions](#)
- [Xray Exploratory App Storage information](#)
- [\[Xray Cloud\] Xray Data Residency location - Germany](#)
- [\[Xray Cloud\] How to update Xray for Jira manually](#)
- [\[Xray Data Center\] How to get Xray Attachments size info on Jira Data Center?](#)