


# [Xporter] How to count or sum values

Counting or summing values can easily be done by following the example below.

```
 ${set(count,0)}  
#{for links}  
#{if (${Links[n].LinkType}.equals('tests'))}  
${set(count,${count} + 1)}  
#{end}  
#{end}
```

## Related articles

- [Xray Exploratory App Storage information](#)
- [\[Xray Cloud\] Xray Data Residency location - Germany](#)
- [\[Xray Cloud\] How to update Xray for Jira manually](#)
- [\[Xray Data Center\] How to get Xray Attachments size info on Jira Data Center?](#)
- [\[Xray Cloud\] Understanding Xray Cloud version nomenclature](#)