

# [Xray] Import via Test Case Importer, Test Step attachment whose name contains spaces

## Problem

If your Test Step attachments contain spaces in their names and the CSV has the exact same name, Xray will not import the attachments.

Please see the example below:

```
1 TCID;Summary;Step/Action;Data;Expected Result;Test Step Attachment
2 1;New Test with Test Step Attachment; verify if the import succeeds;;;test 1.docx
3
```

| Programas > Atlassian > Application Data > Jira > import > attachments |                                    |                     |                           |         | Procurar em attachments |
|--|------------------------------------|---------------------|---------------------------|---------|-------------------------|
|  | Nome                               | Data de modificação | Tipo                      | Tamanho |                         |
|  | AMGT-1931 (11)                     | 05/02/2021 09:33    | Adobe Acrobat Document    | 20 KB   |                         |
|  | CSVConverter Server_attachments_V1 | 16/02/2021 14:44    | Microsoft Excel Worksheet | 14 KB   |                         |
|  | issues (4)                         | 16/02/2021 14:45    | Microsoft Excel Worksheet | 12 KB   |                         |
|  | test 1                             | 24/02/2021 14:24    | Microsoft Word Document   | 104 KB  |                         |

When importing, you'll see the message below:

✓ 1 projects and 1 issues imported successfully!

### ⚠ Import completed with 2 warnings:

- Attachment file not found or not readable, skipping: C:\Program Files\Atlassian\Application Data\Jira\import\attachments\test
- Attachment file not found or not readable, skipping: C:\Program Files\Atlassian\Application Data\Jira\import\attachments\1.docx

### What now?

You can [download a detailed log](#) of this import. You can also [save the configuration](#) for future use.

[Import another project.](#)

[View recently created Issues.](#)

## Solution

To overcome this situation, please replace all spaces by **%20** on the CSV.

```
1 TCID;Summary;Step/Action;Data;Expected Result;Test Step Attachment
2 1;New Test with Test Step Attachment; verify if the import succeeds;;;test%201.docx
3
```

Then the import will succeed!

✓ 1 projects and 1 issues imported successfully!

### What now?

You can [download a detailed log](#) of this import. You can also [save the configuration](#) for future use.

[Import another project.](#)

[View recently created Issues.](#)