Working in regulated environments and ensuring compliance using Xray

- Overview
- · Ways to ensure regulatory and compliance needs
 - Process
 - Implement your own-defined project organization, with fine control over project entities
 - Implement fine Access control and Permissions
 - Use custom defects with their own semantics and decide where to store them
 - Define what is a requirement and track them at multiple levels
 - Track the relevant requirements across multiple versions and/or environments
 - Implement Workflows on testing entities to have explicit control over the process
 - Sign using e-signatures to track explicit reviewal/approval and ensure data integrity
 - Facilitate reviewing, also during test execution
 - Use detailed, trackable and yet flexible Test Planning
 - Track testing tasks with full Assignment and Accountability
 - Enable Customization to fine-tune the tool to your overall rigorous process
 - Data
 - Record all meaningful testing evidence
 - Ensure data persistence, history and change tracking
 - Ensure no data tampering
 - Export data in human-readible formats and automate data snapshots
 - ^o Risks
 - Handle risks with proper Risk Management and Risk-Based Testing
 - Mitigate risks by fostering clarity and facilitating collaboration, including on all testing activities
 - Trace relationship between entities, up to the code
 - Facilitated diagnosis and Root-Cause Analysis
 - ^o Learning
 - Facilitated training resources to improve knowledge and ensure a seamless adoption
- Standards and regulatory requirements

Overview

Organizations working in highly regulated markets (e.g., medical/health, pharmaceutical, security, automotive, aerospace, defense), usually have to comply with specific standards or some regulatory requirements that apply to them and the products they are responsible for.

As an example, ensuring safety is essential for organizations developing medical devices.

A strict control over the development process (testing included), release process, and its maintenance is required. Risk management is core to all activities.

In order to have a proper auditable process in place, that is compliant with high-demanding regulatory requirements, we need to:

- Ensure persistence of historical data & change tracking
- Ensue that historical data cannot be tampered
- Ensure that certain items can only be modified if people are allowed to do so
- · Ensure it's possible to identify who is responsible for what
- · Identify the relationship between entities
- Ensure testing has been performed and that acceptance criteria has been covered
- · Proof of the exact testing/checks that were performed
- Ensure diagnosis is facilitated and can be easily performed
- Ensure effective risk management is in place

Ways to ensure regulatory and compliance needs

Process

Overall, the process must be adjustable, controllable, documentable, clear, and tasks must be repeatable and auditable. Diagnosis should also be facilitated, to be able to understand events. On parallel, we must be able to properly manage risks.

Among others, we need to:

- implement a tailored, auditable, and controlled process (e.g., by configuring the project orgazation, by defining the semantics of entities, by enforcing rules & workflows for testing entities)
- support planning, including at testing level (i.e., using Test Plans)
- ensure tasks, including the ones derived from testing, are complete (i.e., by using tailored Xray issues)
- verify and analyze software requirements from multiple perspectives
- support unit, integration and system testing (i.e., by supporting diverse test automation frameworks alongside manual and exploratory testing)
- enable regression testing (i.e., by having tailored Test Sets or Test Plans for that)
- ensure software verification is complete (i.e., using coverage information)
- document released versions, including testing effort (i.e., by generating documents containing all the relevant data, including testing evidence)

facilitate software problem resolution processes (i.e., by using reports such as the Traceability one)

Implement your own-defined project organization, with fine control over project entities

Xray supports different ways for organizing your project related items. This enables teams to adapt usage of the tool with the way they need or to the way they are organized functionally. But more than that: it enables teams to enforce or apply different rules to different entities.

The common scenario is to have an all-in-one approach where standard issue types (e.g. Story, Bug, Task) live alongside testing issue types (e.g. Test, Test Execution, Test Plan).

However, some teams prefer to have testing entities on a separate Jira project to have finer control over the process. Other teams prefer to have defects on a distinct project, or even on a remote Jira instance for security/business reasons.

All these possible project organization scenarios are possible and allow teams to apply more restricted rules on the related entities.

In the following scenario, two Jira projects are used: one mainly for the standard development/coding tasks and another one for testing purpose. This one of multiple configuration possibilities you can implement.



Even though you can be compliant with an all-in-one approach, Xray provides you the flexibility to even better suit your needs.

Learn more:

Project Organization Use Cases

Implement fine Access control and Permissions

Organizations working in regulated environments need to be able to control the access and the permissions on project artefacts, including the ones derived from testing activities.

Access and permissions for Jira issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution) are handled in the same way as for any other issue type in Jira.

It's also possible to restrict execution of Test Runs to its assignee, so that only the assignee can update its contents.

Learn more:

- Advantages of using Jira issues
- Configuration to restrict execution of tests to the Test Run's assignee

Use custom defects with their own semantics and decide where to store them

Semantically, and to make it clear and be able to apply different rules, it can make sense to have different issue types than the traditional "Bug."

In Xray, it's possible to define the issue types to be handled as "defects." Therefore, whenever reporting a bug, the team can use the Bug issue type or any other custom issue type where they need.

Defects can also be covered explicitly with tests (if configured as "requirements"/coverable issue types), for explicit verification of the underlying bug fixes.

Issue Type Mapping

Requirements and Defects are two concepts commonly related to Tests. A Requirement represents a singular documented fault in a computer program or system that produces an incorrect or unexpected result, or causes it to behave in unintend and a Defect.

Available Issue Types	Requirement Issue Typ	Defect Issue Typ	es
O Test	Fpic	🕄 🚺 Bug	8
Test Set	H New Feature	Incident	0
Test Execution	Story	Problem	8
Pre-Condition	Improvement	8	
🗾 🗾 Test Plan	Incident	8	
Incident			
🔁 Change			
🕒 Sub-task			
I Technical task			

Defects can be reported on the same project alongside other project issues, or can be reported on a separate Jira project. Defects can also be reported on a separate but connected Jira instance, if you wish to do so.

Learn more:

- Issue Type Mapping
- Requirements and Defects

Define what is a requirement and track them at multiple levels

Projects usually have multiple levels of requirements (e.g. Epic>Story). Some broad/complex needs may be addressed in smaller requirements. Value can therefore be decomposed in these different layers and it's important to track it and these layers.

In Xray, a "requirement" is any issue that can be covered with tests, no matter their type. The team can define which issue types can be handled as such, even their own custom issue types (e.g., "Feature").

Issue Type Mapping

Requirements and Defects are two concepts commonly related to Tests. A Requ fault in a computer program or system that produces an incorrect or unexpecte and a Defect.

vailable Issue Types	Requirement Issue	Types
o Test	Fpic	8
Test Set	H New Feature	×
Test Execution	Story	×
Pre-Condition	Improvement	×
🗾 Test Plan		
Incident		

Xray provides multiple levels of requirements. It also provides different ways to define this hierarchical relationship (e.g., using issue links, or sub-tasks)

Epic and Story issues, usual in Agile environments, can be covered directly by testing. Coverage made on the Story issues can automatically be tracked on the related Epic.



- Issue Type Mapping
- Requirements and Defects

Track the relevant requirements across multiple versions and/or environments

Requirements exist beyond the scope of a specific version. Besides, a specific requirement may be used in different contexts (e.g., browsers, mobile devices).

Therefore we need to be able to track the status of requirements throughout time/versions and also on the different scenarios where they will be used. This (coverage) status is based on the integrated testing results, include the ones from test automation.

We may want to perform this analysis at high-level (i.e., project), or for a/some specific requirement(s).

Xray allows you to answer questions such as:

- · Are the requirements covered by any tests whatsoever?
- What were the requirements tested for these version? And what's their status based on the related testing? What's their completeness?
- How are the requirements implemented in an earlier version, on this new/other version?

The coverage status for requirements in Xray is multidimensional; in other words, we can analyze requirements from multiple perspectives: the latest testing results for version, or on a given environment, or just considering the results performed in the scope of a Test Plan.

Let's see some examples.

Accordingly with the latest reported results, all medium and major requirements are OK. However, we can see that one requirement is not covered. We can then drill-down if we wish, by clicking on the chart bar.

Overall Requirement Coverage Report Switch report -



On version 1.0, 50% of the requirements related to the "Search" component are having problems. We can see that the epic BOOK-8 is 66,7% complete, because one of the related stories (BOOK-9) has 1 test currently failing on version 1.0.

Some related stories (BOOK-10, BOOK-11) are OK though.

Overall Requirement Coverage Report Switch report ~

Scope: Version; Version: 1.0; Environment: All Environments - Component/s - = Filter(s) - 💵 How to read this report



Requirements with Component/s "Search" and Status "NOK"

View Issues

Show	10	~	entries

					Search	
Key	🖨 Summary	♦ Total Tests	Tests Passed	♦ Tests Failed	♦ Tests Unknown	Completeness
BOOK-8	As a visitor, I can manage my Shopping Basket	3	2	1	0	66.7%
BOOK-11	As a visitor, I can view all the books in my shopping basket	1	1	0	0	100%
BOOK-10	As a visitor, I can remove books from my shopping basket	1	1	0	0	100%
BOOK-9	As a visitor, I can add books to my shopping basket	1	0	1	0	0%
	 Key BOOK-8 BOOK-11 BOOK-10 BOOK-9 	Key Summary BOOK-8 As a visitor, I can manage my Shopping Basket BOOK-10 As a visitor, I can view all the books in my shopping basket BOOK-10 As a visitor, I can remove books from my shopping basket BOOK-9 As a visitor, I can add books to my shopping basket	Key Summary Tatal Tests BOOK-8 As a visitor, I can manage my Shopping Basket 3 BOOK-10 As a visitor, I can view all the books in my shopping basket 1 BOOK-10 As a visitor, I can remove books from my shopping basket 1 BOOK-9 As a visitor, I can add books to my shopping basket 1	KeySummaryTogsFassedBOOK-8As a visitor, I can manage my Shopping Basket32BOOK-10As a visitor, I can view all the books in my shopping basket11BOOK-10As a visitor, I can remove books from my shopping basket11BOOK-9As a visitor, I can add books to my shopping basket10	Key Summary Failed BOOK-8 As a visitor, L can manage my Shopping Basket 3 2 1 BOOK-10 As a visitor, L can view all the books in my Shopping basket 1 1 0 BOOK-10 As a visitor, L can remove books from my Shopping basket 1 1 0 BOOK-9 As a visitor, L can add books to my Shopping basket 1 0 1	Key Summary Total Total Total Passe Total Passe <thtotal Passe <thtotal Passe <thtotal Pa</thtotal </thtotal </thtotal

Learn more:

- Coverage Analysis
- Overall Requirement Coverage Report

Implement Workflows on testing entities to have explicit control over the process

Teams can implement workflows on all Jira issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution).

This will allow them to implement rigorous processes, including on testing entities, leveraged on the flexibility of Jira workflows.

Additionally, Xray provides the ability to further restrict usage of some these entities.

Possible use cases:

- have workflow status to review test specifications
- implement an approval mechanism, having one or more approvers
- make items "read-only" when transitioned to a certain workflow status by setting a Jira property ("jira issue editable")
- restrict usage of Tests in a certain workflow status (see how)
- disallow executions for Test Executions in a specific status (see how)
- reopen/review Tests upon changes on related requirements (example)
- enforce that requirements cannot transition to a given status, unless they are covered or even that those tests are successful (example)

Learn more in:

• Using Jira workflows for testing purpose

Sign using e-signatures to track explicit reviewal/approval and ensure data integrity

Electronic/digital signatures are one of the common mechanisms employed to ensure that document, for example, has been reviewed by one or more people and that no changes happened on the signed document meanwhile.

Xray issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution) can all be digitally signed, using one of many available Jira apps for that purpose. This is something unique, as it provides full control over the core testing activities; not only Tests can be digitally signed, also Test Sets, or even Test Plans.

• available Jira apps for e-signatures

Facilitate reviewing, also during test execution

Review during or after test execution can be implemented.

In Xray, similarly to other issues, Test Execution issues have an assignee. We can use that as the main responsible for the Test Execution, perhaps for defining the list of tests to be run and then for reviewing its results.

The Tests to be run on Test Executions (i.e., the Test Runs) can have their own specific assignee. Therefore, we can have a Test Execution responsible and the individual testers performing the identified testing.

This Test Execution as a whole is assigned to Petr Gonzalez but one of the Test Runs is assigned to another user (Bruno Conde). This can be used as means to have one person responsible for the Test Execution and reviewing the related reported results, while at the same time allowing for someone else to perform the actual testing.

Bookstore / BO Test Exect	oK-31 Ition for Test Plan BOOK-30						
Sedit Q Commer	Assign More v Start Progress Resolve Issue Close	Issue Admin Y					
✓ Details						 Xporter 	
Type:	Test Execution	Status:	REOPENED (View Workflow)			Template	Basic Release Notes
Priority:		Resolution:	Unresolved				
Affects Version/s:	None	Fix Version/s:	1.0			Output format	DOCX
Component/s:	None						+ Export
Labels:	DOCK 20						Export
Test Environments:	None						
Revision:	65d64uva7t6r					 People 	-
Novision.	oodo-tayg/toi					Assignee:	O Petr Gonzalez
× Description							Assign to me
Click to add description	n					Reporter:	💽 Xpand IT Admin
						Votes:	0
✓ Tests						Watchers:	1 Stop watching this issue
Add Tests 🗸						✓ Dates	
						Created:	25/Feb/19 2:06 PM
Overall Execution Status						Updated:	Just now
						Begin Date:	18/Feb/19 2:03 PM
14 pass 1 fa						End Date:	22/Feb/19 2:03 PM
Total Tasts: 16						✓ Agile	
∓ Filter(s)						Active Sprint: View on Board	Sprint 1 ends 18/Mar/19
Apply Rani	2			Show 100 🗸 entries	Columns -		
🔻 Rank	🔷 Key 🛭 🍦 Summary	Test Type #Req	#Def Assignee	🖨 Status			
□ 16	BOOK-36 Manual test of strong password validation	Manual 2	0 Bruno Conde	ТОДО	• …		
□ 15	BOOK-37 Manual test of password reset procedure	Manual 2	0 Petr Gonzalez	PASS	• …		

This enables the implementation of a reviewal process, where Test Execution related results can be reviewed after they're reported; the Test Execution can be transitioned to a status (e.g., "PENDING_REVIEW") and then transitioned to another one (i.e., "CLOSED") when it's reviewed.

We can also create some specific Test Run custom field (e.g., "Reviewer Comment") and make it required for all runs, or just for the ones related to manual scripted test cases.

Project Settings								
Summary	Test P	Edit Test Rur	n Field					
Details	Define Tr							
Audit log	Denne n							
Re-index project		Na	me* Reviewer Cor	nment			Test Types	
Delete project		Descript	ion Comment of	the reviewer	J		GENERIC CUCUMBER MAN	JAL
		Ту	vpe Text Field (mi	ulti-line) 🗸 🗸				
Bug		Test Typ	es* Cucumber ×	Generic ×				
- Epic			Manual ×					
Pre-Condition		Requi	red 🛛 🗹 This test ru	n field is required				
- Story								
- Sub-bug					Update	Cancel		
- Sub-task		_						
- Sub Test Execution								
- Task								
- Test								
- Test Execution								
 2 more issue types 								
2 more issue types Bookstore / Sub Test Execution: BOOK-333 / Ter Test visitors can add books to their	st: BOOK-23 shopping ba	isket				Import Executi	on Results Export to Cucumber 🔺	Return to Test Execution
2 more issue types Bookstore / Sub Test Execution: BOOK-333 / Te Test visitors can add books to their	st: BOOK-23 shopping ba	isket				Import Executi	on Results Export to Cucumber 🔺 I	Return to Test Execution
V 20 more issue types Bookstor / Sub Test Execution: BOOK-333 / Te Test visitors can add books to their Execution Basis FAL	st: 800K-23 shopping ba	isket				Import Executi	on Results Export to Cucumber 🔺 I Assignce: None Executed Riv: Yoand IT Admin	Return to Test Execution Versions: 3.0 Revision: -
Concentration Service	st: BOOK-23 shopping ba	Isket Aug/21 2:38 PM				Import Executi	on Results Export to Cucumber A I Assignce: None Executed By: Xpand IT Admin Tests - environments:	Return to Test Execution Versions: 3.0 Revision: -
Comment	st: B00K-23 shopping ba	Isket Aug/212:38 PM	vertiling Defects (0)	Could Datest Double bit 7	ek Add Defects	Import Executi Execution Evide	Assignet: None Assignet: None Executed by: Xand Ti Admin Tests - environments:	Return to Test Execution Versions: 3.0 Revision: -
Comment	st: BOOK-23 shopping ba	Aug/21 2:38 PM review Comment v	xecution Defects (0)	Greate Defect Greate Sub-Ta	sk Add Defects 🗸	Import Executi Execution Evider	Assignet: None Executed by: Xand Ti Admin Tests - environments:	Return to Test Execution Versions: 3.0 Revision: - Add Evidence V
Comment Comme	st: BOOK-23 shopping ba	ISKet Avag/21 2:38 PM review Comment V	acution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects 🗸	Import Executi Execution Evider	Assignce: None Executed by Xand T Admin Tests - environments:	Return to Test Execution Versions: 3.0 Revision: - Add Evidence V
Comment Co	st: BOOK-23 shopping ba	Aug/21 2:38 PM	vecution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects 🏏	Import Execution Execution Evider	Assigner: None Executed by: Xand T Admin Tests - environments: toce (0)	Return to Tast Execution Versions: 3.0 Revision: -
Comment Co	st: BOOK-23 shopping ba	Aug/21 2:38 PM	vecution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects 🗸	Import Execut Execution Evider	Assigner: None Assigner: None Executed by Xgand T Admin Tests - environments:	Neturn to Test Execution Versions: 3.0 Revision: - Add Evidence V
Comment Co	st: BOOK-23 shopping ba	Aug/21 2:38 PM	vecution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects v	Import Execut	Assigner: None Assigner: None Executed by Xgand IT Admin Tests - enrivonments: hole (0)	Return to Test Execution Versions: 3.0 Revision: - Add Evidence
Concentration Concentration Comment Comment Comment Comment Test Description Test suce Links (3) Custom Fields Knewer Comment	st: BOOK-23 shopping ba	ssket Aug/21 2:38 PM review Comment ↓ E	recution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects 🗸	Import Execution Execution Evider	Assigner: None Assigner: None Executed by Xgand T Admin Tests - enrivonments:	Neturn to Test Execution Versions: 3.0 Revision: - Add Evidence
Comment Co	st: BOOK-23 shopping ba Finished On: 25/ P	ssket Augg212:38 PM review Comment ▽ E + → x	vecution Defects (0)	Greate Defect Greate Sub-Ta	sk Add Defects 🗸	Import Execution Execution Evider	Assignce: None Executed by: Xgand T Admin Tests - environments: toce (0)	Return to Test Execution Versions: 3.0 Revision: - Add Evidence
Comment Co	st: BOOK-23 shopping ba Paisted On: 25/ P	Asg/21 2:38 PM	vecution Defects (0)	Greate Defect Greate Sub-Ta	sk Add Defects 🗸	Import Execution Execution Evider	Assignce: None Executed by Xgand T Admin Tests - environments: total (0)	Return to Test Execution Versions: 3.0 Revision: - Add Evidence
Comment Co	st: BOOK-23 shopping ba Finished On: 25/ P	ssket Aug/212:38 PM review Comment v E	vecution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects 🗸	Import Execution Evacution Evider	Assignce Nore Assignce Nore Executed by Xead TAdwar environments:	Return to Test Execution Versions: 3.0 Revision: - Add Evidence v
Comment Co	st: BOOK-23 shopping ba Finished On: 25/ P	ssket Aug/212:38 PM review Comment v E	vecution Defects (0)	Create Defect Create Sub-Ta	sk Add Defects 🗸	Import Execution Evacution Evider	Assignce None Assignce None Executed by Xand IT Admin environments:	Return to Test Execution Versions: 3.0 Revision: - Add Evidence v V
Comment Co	At: BOOK-23 shopping ba Privated On: 256 P	ssket Aug/212:38 PM review Comment v E	vecution Defects (0)	Create Defect Create Bub-Ta	sk Add Defects 🗸	mport Execution Execution Evide	Assigne: None Executed by: Spaced TAdmin Tasks - environments:	Return to Test Execution Versions: 3.0 Revision: - Add Evidence v v v
2 A construction 4 A construction 4 A construction 2 A	et: BOOK-23 shopping ba	sket Aug/21 2:38 PM review Comment E	recution Defects (0)	Create Defect Create Bub-Ta	ak. Add Daffeets. 🗸	mport Execution Evides	Assigne: None Assigne: None Executed by: Spaced Tradeous environments:	Return to Test Execution Versions: 3.0 Revision: - Add Evidence

During execution of a test and its revision, we may find it useful to report a step as having an acceptable failure (e.g., "IRRELEVANT_FAIL"). We can then decide to mark the overall Test Run with a status (e.g., "FAIL_DISCARD") that won't mark the related requirement as being NOK, such as UNKNOWN or even OK if we want.

Test Statuses

Manage custom Test Run statuses for Xray

Name	Description	Final	Color	Requirement Status
PASS	The test run has passed			ок
TODO	The test run has not started			NOTRUN
EXECUTING	The test run is currently being executed			NOTRUN
FAIL	The test run has failed			NOK
ABORTED	The test run was aborted			NOTRUN
BLOCKED				NOTRUN
PENDING				UNKNOWN
FAIL_DISCARD	There was a minor issue but nothing relevant			UNKNOWN

Test Step Statuses

Manage custom Test Step statuses for Xray

Name	Description	Color	Test Status
PASS	The test step has passed		PASS
TODO	The test step has not started		торо
EXECUTING	The test step is currently being executed		EXECUTING
FAIL	The test step has failed		FAIL
SKIP	The test step has been skipped.		PASS
IRRELEVANT_FAIL	There was a minor issue with this step but nothing relevant		FAIL_DISCARD

Bookstore / Test Plan: BOOK-30 / Test Execution: BOOK-31 / Test: BOOK-36 Manual test of strong password validation

Execution S	Status 📕 FAIL_DISCARD 🗾 🚺	Finished On: -				Assignee: Executed By: Tests environments:	Bruno Conde Xpand IT Admin -	Versions: 1.0 Revision: 65d64uyg7	't6r
Com	iment	Preview Comment 🗸	Execution Defects (0)	Create Defect Create Sub-Task	Add Defects 🗸	Execution Evidence (0)		Add Evidence	~
E x	ecution Details								
Test Des	scription								~
Test Issu	ue Links (1)								^
tests	BOOK-38 As a use	r, I want to be enforced to have a strong password	so my account is properly secure	d				RESOLVED	
Custom	Fields								~
Test St	eps (4)								~
1	Action		Data			Expected Result			
	Open the Change Password screer	n by selecting option "My Profile > Password"	None			None			
	Actual Result ¥	Comment 📮 🕀 Defects	① (0) ⊕ E	vidence 👁 (0) 🔶			Step State PASS	₽	
2	Action		Data			Expected Result			
	Fill the password fields with data		Current Password: passw0r New Password: p4ssw0rd Confirm New Password: p4	rd ssw0rd		Error: "Current password is incorrect"			
	Actual Result ¥	Comment 🔲 🕀 Defects	⊙ (0) ⊕ E	evidence 💿 (0) 🔶			Step State IRRELEVA	NT_FAIL	

Use detailed, trackable and yet flexible Test Planning

Even though plans can change (especially in an Agile context), being able to define a plan, no matter its level of detail, is something usually required.

Some testing activities, including verification, can be planned upfront.

Xray provides an entity specifically for this purpose: the Test Plan. The Test Plan can be used more strategically, to define and track and assign testing activities to be performed.

In Xray, teams can have one or more Test Plans to track different testing efforts, for example related with different types of tests, or different risks, or even explicitly for regression testing.

The Test Plan can be as detailed as needed and documents can be added and linked to it. A Test Plan is also assigned to a user; it can be prioritized, labelled, and be explicitly one work item of the Sprint or of the Kanban board.

In the following example, we can see the Test Plan being tracked as an item and handled as part of the Sprint, similarly to other on-going project issues.

Sprint 1



Learn more:

- Planning Tests
- Tips for planning tests
- Some examples of using Test Plans in Scrum context
- Agile Board Enhancements

Track testing tasks with full Assignment and Accountability

Xray issues (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution) can be assigned and watchers can be added to them.

That means, for example, that whenever a Test is modified, you can get notified.

Bookstore / BOO Test visitor	s can remove bo	oks from th	neir shoppir	ıg basket				
dit Q Comment	Assign More 🗸	Start Progress	Resolve Issue	Workflow 🗸	Admin 🗸			
etails							 Xporter 	
ype:	Test			Status	: 	PEN (View Workflow)	Template	Basic Releas
ffects Version/s:	None			Fix Ver	sion/s:	resolved	Output format	DOCX
omponent/s:	None							.↓. Export
abels: est Repository Path:	Shopping Basket							
							✓ People	
escription							Assignee:	🚳 Bruno Cor
ick to add description	I							Assign to me
et Dotaile							Reporter:	Petr Gonz
	Cucumber						Votes:	0 Vote for t
ypc.	oucumber						Watchers:	1 Stop wate
cenario Type:	Scenario							
cenario:	Given I am on shoppi	ng basket pag	e				✓ Dates	
	When I click the ren	nove from bask	et button for	a listed boo	k		Created:	25/Feb/19 1:3
	The book is del	eted from my	Shopping paske	T. C.				

Ensure issues get done by assigning them to users and tracking them using workflows (more info ahead), no matter if you're dealing with the specification of a test case or the execution of a bunch of tests within a given Test Execution.

Individual Test Runs can also be assigned and it's possible to notify the assignee using traditional email notifications, just like any other issue in Jira.

Learn more:

Email Notifications

Enable Customization to fine-tune the tool to your overall rigorous process

For defining a more rigorous process, teams need the ability to customize usage of the tool.

This includes, among others, the ability to:

- add custom fields on any testing entity, including all Jira issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution) and also on Test steps and on Test Runs
- implement additional customizations (e.g., using ScriptRunner, Automation for Jira, Cprime Power Apps)
- · integrate with other Jira apps to widen the feature set provided by Xray itself

Learn more:

- · Advantages of using Jira issues
- Integration with ScriptRunner
- Integration with Automation for Jira
- Integration with Cprime Power Scripts, Power Custom Fields, and Power Actions

Data

Record all meaningful testing evidence

Teams can follow different approaches/styles for testing: scripted (i.e. test cases and "automated" test scripts) and exploratory.

No matter the testing approach, Xray can provide visibility of testing results, including evidence, in one place: Jira.

Xray allows you to identify:

- · version and revision of the SUT
- environment (e.g., browser, device)
- test result/status
- detailed results (e.g. steps)
- screenshots, videos or any other file-based evidence
- execution logs
- any reported comments

Whenever manually executing scripted test cases, we can report results at the step level, and attach some screenshot as evidence, for example:

Atlas Mobile App / Test Plan: ATLAS-17 / Test Execution: ATLAS-19 / Test: ATLAS-8 Manual test of strong password validation		Dataset Return to Test Execution Previous Next
Test Details MANUAL		
> Custom Fields		
> Test Description		
∧ Test Steps (4)		
1 Action	Data	Expected Result
Open the Change Password screen by selecting option "My Profile > Password"	None	None
Actual Result > Comment Comme	(0) ⊕ Evidence ♥ (0) ⊕	Step State PASS
2 Action	Data	Expected Result
Fill the password fields with data	Current Password: passw0rd New Password: p4ssw0rd Confirm New Password: p4ssw0rd	Error: "Current password is incorrect"
Actual Result > Comment 🗖 🕞 Defects 🕚	(0) ⊕ Evidence ♥ (0) ⊕	Step State PASS
3 Action	Data	Expected Result
Close error message and fill again the password fields with data	Current Password: P4ssw0rd New Password: password Confirm New Password: password	Error: "New password is too simple"
Actual Result * Comment 🗖 🔶 Defects 🔿	(0) ⊕ Evidence ♥ (0) ⊕	Step State PASS
4 Action	Data	Expected Result
Close error message and fill again the password fields with data	Current Password: P4ssw0rd New Password: P4ssw0rd Confirm New Password: P4ssw0rd	Information message: "Password successfully changed"
Actual Result ¥ Comment 🔲 Defects 3	(1) ⊕ Evidence ● (1) ⊕	Step State FAIL +
	Screenshot_1626039796	
> Activity		

Detailed information from multiple test automation frameworks can also be imported to Xray, and tracked similarly to other tests.

This includes automation frameworks such as Robot Framework, where you can see the detailed keyword-level information.

1	Robot / Test Plan: ROB-12 / Test Execution: ROB-17 / Test: ROB-18 Valid Login		Export Test as Text	Return to Test Execution Next >
	Execution Status PASS		Assignee: / Executed By: A Tests - environments:	Administrator Versions: - dministrator Revision: -
(고 (고	Comment Preview Comment v	Execution Defects (0) Create Defect Create Sub-Task Add Defects v	Execution Evidence (0)	Add Evidence 🗸 🗸
4	Execution Details			
ore Second	Test Description			~
e D	Test Issue Links (1)			^
\bigcirc	tests ROB-11 As a user, I can login the web application			IN PROGRESS
	Test Details			^
	Test Type: Generic Definition: Login Tests.Valid Login.Valid Login			
	Results			^
	Context	Output	Dura	tion Status
	Open Browser To Login Page	-	3	sec PASS
	Input Username	-	24.000	ms PASS
	Input Password	-	22.000	ms PASS
Ö	Submit Credentials	-	46.000	ms PASS
>>	welcome Page Should be Open	-	7.000	ms PASS

If adopting BDD frameworks, such as Cucumber, we can also see detailed information about the Gherkin statements and deep-dive into the automation logs or evidence (e.g., screenshots) taken by the automation.

Calculator) simple ii	/ Test Execution: CALC-7938 / Test: CALC-7936 nteger multiplication	ą	Import Execution Results	Export to Cucumber	Return to Test Execution	Pre
Result	S					
	Context			Du	ration Status	
	·			2.16	67 ms FAIL	
	Steps					
	Given I have entered 3 into the calculator			0.09	92 ms PASS	
	And I have entered 0 into the calculator			0.70	06 ms PASS	
	When I press multiply			0.04	17 ms PASS	
	Then the result should be 0 on the screen			1.32	22 ms FAIL	
	<pre>java.hug.nsser.townick.to</pre>	efinitions.java:36) mber-java-calc/featur	es/2_CALC-7935.featu	ce:11)		
Test Details				,	~	
Scenario: Scenario:	Scenario 1 Given I have 42 cukes in my belly 2 when I wait 1 hour 3 Then my belly should growl					
Results					~	
Cont	avt		Duration	Status		
			288 millisec	PASS		
	Hooks					
	Before Cukes.setUp()	❹ (2)	0 millisec	PASS		
	After Cukes.tearDown()			PASS		
	Background	evidence_step_30	_0.png			
	Given buy a few cukes	evidence_step_30	_1.jpg	PASS		
	Steps	evidence_step_30	_2.txt	74.66		
	Given I have 42 cukes in my belly	<pre> widence_step_30 widence_</pre>	_3.html	PASS		
	When I wait I hour	(%) evidence_step_30	_4.xml	PASS		
	iner my bely should grow			PASS		

Xray also supports exploratory testing using a desktop app (Xray Exploratory App) that can integrate with Xray to bring the best of both worlds: have exploratory testing evidence tracked in Jira, be accessible by the team, and reflect on the related requirements.

Hello XET App / Test Execution: HX-194 / Test: HX-189 my test to edit		Execute with Exploratory A	Import Exe	cution Results		
				↑ Return	to Test Execution	Next >
Execution Status FAILED 4/2 E				Assigne	e:	Versions: -
Started On: 4/Dec/2019 04:30 PM				Unassi	gned	Revision: -
Finished On: 4/Dec/2019 06:43 PM				Execute Nelson	ed By: Pereira	
				Test En	vironments: -	
Comment	•	Execution Defects (1)	•	Execution Evidence (2)		•
Session Started • 18h36 04-12-2019		HX-204 my defect documented		C xrayVideo_2019	266.7 kB 4/Dec/2019	06:41 PM
O0:00:52 • Note [Idea] A great note about this	_			Test Session-D	2.1 MB 4/Dec/2019	06:43 PM
Execution Details						

- Execute Tests
- Vast collection of test automation tutorials showcasing integrations with Xray
 Performing exploratory testing and integrating it with Xray

Ensure data persistence, history and change tracking

In order to enable auditing and facilitate diagnosis, data must be stored, and changes, whenever applicable, need to be clearly identified.

In Xray, all data is persisted and can be easily tracked using a historical timeline.

All changes on Jira issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution) are tracked similarly to other issue types in Jira.

One of those examples include Tests themselves.

 Activity 			
All Comments W	Vork Log History Activity		î
O Administrator crea	ted issue - 24/Jun/19 10:20 AM		
O Administrator made	e changes - 24/Jun/19 10:20 AM		
Field		Original Value	New Value
Component/s			Account [10900]
O Administrator made	e changes - 24/Jun/19 10:21 AM		
Priority	Trivial [5]		Major [3]
O Administrator made	e changes - 24/Jun/19 10:21 AM		
Manual Test Steps			[Step: Step] [Data: Data] [Expected Result: Expected Result]
O Administrator made	e changes - 24/Jun/19 10:21 AM		
Manual Test Steps			[Step: Open the Change Password screen by selecting option "My Profile > Password"] [Data:] [Expected Result:]

Test Runs also have an activity section where its changes are tracked.

Bookstore / Manual 1	Test Plan: BOOK-30 / Test Execution: BOOK-31 / est of strong password validation	Test: BOOK-36		📭 🖪 Dataset	Return to Test Execution	Previous
	Actual Result ¥ Comment 📮 🤇	Defects ①	(0)	Step State 📕	PASS ←	
4	Action Close error message and fill again the password fields	s with data	Data Current Password: P4ssw0rd New Password: P4ssw0rd Confirm New Password: P4ssw0rd	Expected Result Information message: "Password successfully changed"		
	Actual Result ¥ Comment 🔲 🤇	Defects ①	(0) ⊕ Evidence ⊘ (0) ⊕	Step State	PASS ←	
Acti	vity xadmin changed status from EXECUTING to PASS. Just row xadmin edited STEP 4 C Changed field "Status" from TODO to PASS Just row xadmin edited [STEP 2] C Changed field "Status" from TODO to PASS Just row xadmin edited [STEP 2] C Changed field "Status" from TODO to PASS Just row					
	xadmin changed status from TODO to EXECUTING. Just now					

Test Runs

Ensure no data tampering

Historical results (i.e. Test Run details) can't be modified. The same applies to past changes made on Jira issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution).

It is also possible to make Xray issue-based entities read-only. Besides, test specification cannot be modified during execution of the related test.

Export data in human-readible formats and automate data snapshots

All core entities, including Test Runs (i.e. results), can be exported to PDF, Word, or Excel documents, using fully customizable documents in terms of layout.

This is a way to obtain a formal, readable, copy of the relevant test data, no matter if it's related to test specification or execution.

Two options exist to achieve this: either using the built-in Document Generator capabilities, or by using the more complete and general purpose Xporter App.

You can start by defining a template, or downloading and customizing an existing one from the template store, with all the data to be embedded, logos and other information (e.g., legal disclaimers)

							Test R	eport					
	This te	mplate	creates a t	test report from t	he sel	ection	ofmultipl	e issues, c	reated using X	iray for JIR	A.		
						D	ownload T	emplate 🕯					
						Do	wnload Sa	mple File	*				
				4					5		Test	Nuez	5
2. Manual Te	sts				3. Auto	omated Tests				3.1.7. Key	lest P	Summary	
2.1. Manual	Test EX-62 - Po	wer it On M	1		3.1. Au	tomated Test	EX-58 - Funcionam	ento de colmeias em	ambientes agrestes	EX+88		Test Plan to validate Templates - EK-62 and EK-58	
2.1.1. Status of v2.0 - FAIL	the Last Execution				3.1.1. St v2.0 - EXE	tatus of the Las ECUTING	t Execution						
2.1.2. Pre Cond	litions				3.1.2. Pre Conditions								
None					Key	Summary		Condition					
2.1.3. Requirer	Requirement Su	mmari			PX 62	Ann ann Linne		Given The Dark side of : many abilities, some co	he force is a pathway to isidered to be unnatural				
EV. 69	You talking to me	3			0.00	100 900 0100		Ask Is it possible to lear Expect Not from a Jedi	n those powers				
214 Descript	ion				3.1.3. Re	equirements							
does it work?					Requireme	ent Key R	equirement Summary						
yes, it seems to					EX-70	P	ione home						
2.1.5. Test Pro	cedure				EX-68	Y	ou talking to me?						
Step Number	Step	Data	Expected Result		3.1.4. D	escription anacidade desta	is instala <i>r lies</i> até à <u>eva</u> i	utto.					
1	Frankly, my deart, i don't give a	1939	GONE WITH THE WIND		315 T	est Procedure							
2	I'm gonna make	1972	THE CODFATHER		Scenario	carriecture							
	him an offer he				Given abel In order to	ihas o produce honei							
	Carl Cherose.				Then colm	neias							
2.1.6. Test Set	s Summary		Te	est Count	I want to Given								
EX-63	(porter Performance All 1	fests	5		3.1.6. Te	est Sets							
EK-61	(porter Performance Man	ual Tests	2		Key	Summary			Test Count				
2.1.7. Test Plan	ns				EX-63	Xporter P	erformance All Tests		5				
EX-88	Fest Plan to validate Tem	plates – EX-62 ar	nd EX-58		EX-56	xporter P	prormatice Automated Ter	0.0	1.				
TEST REPORT - AUTO	IMATICALLY GENERATED			4	TEST REPOR	T - AUTOMATICALL	Y GENERATED		5	TEST RE	PORT - A	UTOMATICALLY GENERATED	6

Test Plan Advanced with Cover Page (Xray 5)

This template provides a way to see a Test Plan with a little more detail. You can see the Test Run details, Test Steps details, attachments, evidences, and defects of normal and parameterized tests. This template is compatible with versions above 5.x.x



With Xporter and DocGen it's possible to export the information of an issue (e.g., a Test Plan), right from the issue screen (among other places).

📲 Jir	Dashboards 👻 Projects 👻 Issues 👻 Boards 👻 Structure 👻 Xporter Reports	Jone Conta		Q Search	土 🧉 🛛 🗘 🌑
7	Bookstore / BOOK-30 Test Plan for v1.0 V Edit O Comment Assim More ~ Tests Pass Tests failed Admin ~	Xray - Document Generator		e e	を Doc. Generator 一奇 Expert マ
8		Template Ø	- Marantan		
	Type: Test Plan	Test Plan Advanced with Cover Page (Xray 5)	× xporter		
۵	Priority: O Trivial	Output Format	Template	Basic Release Notes	∨ ∅
<u>[~*</u>	Affects Version/s: None		Output format	DOCX	~
	Component/s: None Labels: default			🛃 Export	
\$? ∭	> Description	Export Close	v People		
4	✓ Tests		Assignee:	Bruno Conde	
	Tast Dian Board	L Create Test Evecution v L Add	Reporter	Assign to me	
	- Tear Plan Dual u	+ Cleare Test Execution - + Aut	Votes:	0	
	Overall Execution Status		Watchers:	1 Stop watching this issue	
	18 PASS 2 FAIL		✓ Dates	25/Eeb/10 2:04 DM	
			Updated:	03/Dec/19 10:50 AM	
	Total Tests: 20		Begin Date:	18/Feb/19 2:03 PM	
			End Date:	22/Feb/19 2:03 PM	
	← Filter(s)		✓ Agile		
	■ *	Show 10 v)entries All Environments - Columns	Active Sprint: View on Board	Sprint 1 ends 18/Mar/19	
	Key Summary Requir	ements #Test Executions Issue Assignee Latest Status			
	BOOK-18 Test a visitor can change his locale BOOK-	5 1 Bruno Conde PASS			
	BOOK-17 Test a logged in visitor can edit the default address BOOK-	1, BOOK-4 1 Bruno Conde PASS			

With Xporter it's also possible to export issues in bulk; this can be useful to export a set of Tests or Test Executions, for example.

Bulk Operation		
Choose Issues Selected 3 issues from 1 project(s)	Step 2 of 4: Choose Operation Choose the operation you wish to perform	n on the selected 3 issue(s).
Choose Operation	 Edit Issues 	Edit field values of issues
Operation Details Confirmation	O Move Issues	Move issues to new projects and issue types
- oommaaon	 Transition Issues 	Transition issues through workflow
	O Delete Issues	Permanently delete issues from Jira
	O Watch Issues	Watch all the selected issues. You will receive notifications when any of these issues are updated.
	O Stop Watching Issues	Stop watching all the selected issues. You will no longer receive notifications when any of these issues are updated.
	 Export Issues (Xporter) 	Export issues using Xporter

With any of the two solutions, and just for reference, it's possible to:

- generate a custom PDF document with test cases and their specification, and the link to the related requirements (e.g., the typical "notebook of tests)
- generate a custom Word document with the current detailed results of a Test Plan, and all related iterations (i.e. Test Executions)

With Xporter it's possible to automate the generation of these documents and, for example, generate them upon a transition of a workflow, or attach to an existing Confluence page, or even send them to some email.

Administration & Search JIRA admin

Applications Projects Issues Add-ons User management System

Add Post Function To Transition

	Name	Description					
	Assign to Current User	Assigns the issue to the current user if the current user	r has the 'Assignable User' permission.				
	Assign to Lead Developer	Assigns the issue to the project/component lead develo	pper				
	Assign to Reporter	Assigns the issue to the reporter					
	Create Perforce Job Function	Creates a Perforce Job (if required) after completing the	e workflow transition.				
	Fire Event	Fires an event that can be processed by listeners.					
	Generate Change History	Updates change history for an issue and stores the issue to the database.					
	Notify HipChat	Send a notification to one or more HipChat rooms.					
	Trigger a Webhook	If this post-function is executed, JIRA will post the issue	ue content in JSON format to the URL specified.				
\bigcirc	Update Issue Field	Updates a simple issue field to a given value.					
0	Update Issue Status	Sets issue status to the linked status of the destination workflow step.					
۲	Xporter for JIRA Create Document Post Function	Create a document based on the issue fields.					
0	Xporter for JIRA Send Report Post Function	Send a report by email.					

Add Cancel

Learn more:

- Built-in Document Generator
- Xporter app Xporter Template Store

Risks

Handle risks with proper Risk Management and Risk-Based Testing

Handling risks is an intrinsic part of good testing and is essential to organizations that work in highly regulated environments.

Xray supports Risk-Based Testing (RBT) and allows you to define risks at different levels: project, requirement or at the test-level.

Depending on the exact need, implementation of risk management can be accomplished using Jira built-in capabilities or through an additional app.

No matter the approach, we can use risks to pick the requirements and/or the Tests that we need based on risk criteria.

Add Tests to Test Execution CALC	-370	2			As	signee	Issue Assignee	•
Select Search JQL								
Filter(s) –							Col	umns -
Project Calculator (CALC) ×		↓ Issue Type		Summary	♣ Risk Level	♦ Probab	oility 🍦 Impact	Risk ▼ Score
Test Type		0	CALC-3703	ability to perform clear / start new operations from scratch	L5: Severe	4	4	(((16)))
Choose the Test Type		0	CALC-1202	CanAddNumbers	L3: High	2	4	((8))
Contains text		0	CALC-1203	CanDoStuff	L2: Medium	1	4	(4)
		0	CALC-3706	check the history of operations	L1: Low	1	2	(2)
Risk Score between 2 and 16 The Risk Score Field for Risk Management Clear Q Search	Show	ing 1 to 4 of 4	4 entries			First	Previous 1	Next Last
V Hide Tests in non-executable Statuses						Add sele	Add all (4) Cancel

Whenever risks are defined at requirement level, we can analyze coverage for all requirements on our project and, for example, decide to make a release or not based on the status of the most critical requirements.

Overall Requirement Coverage Report switch report -



Learn more:

- Performing Risk-Based Testing (RBT) with Xray
- Risk Management
- Risk-Based Testing

Mitigate risks by fostering clarity and facilitating collaboration, including on all testing activities

The best way to avoid misunderstandings is to clarify them ASAP and make sure doubts don't get lost. This is, in itself, a way of risk mitigation.

Comments and evidence (e.g., reference documentation) can be added on all Xray issue based entities (i.e. Test, Pre-Condition, Test Set, Test Plan, Test Execution, Sub-Test Execution) and also on Test Runs.

 Details 					 Xporter 	
Type:	O Test	Status:	OPEN (View Workflow)		Template	Basic Release Notes
Priority:	O Trivial	Resolution:	Unresolved			
Affects Version/s:	None	Fix Version/s:	1.0		Output format	DOCX
Component/s:	None					.t. Export
Labels: Test Repository Path	Shopping Basket					
rest Repository Patri.	Shopping basket				- Provide	
> Description					 People 	
boonplion					Assignee:	Bruno Conde
✓ Test Details						Assign to me
Type:	Cucumber				Reporter:	Xpand IT Admin
					Votes:	0
Scenario Type:	Scenario				Watchers:	 Stop watching this issue
Scenario:	Given I am on a product detail page					
	And I click the add to basket button				✓ Dates	
	Then the product is added to my shopping basket				Created:	25/Feb/19 1:39 PM
				A Fally Change	Updated:	Just now
				Edit Steps		
					 Agile View on Reard 	
> Pre-Conditions					view on board	
> Test Sets						
> Test Plans						
> Test Runs						
> Attachments				•••		
> Issue Links				+		
> Structure				Q		
 Activity 						
All Comments W	/ork Log History Activity					
V O Xpand IT Admir	added a comment - Just now			017		
Brune Cond	have any accurity state one should according to this flat 2					
Bruno Conde are t	nere any security risks we should consider in this flow?					

If your team decides you need one or more specific fields to embed some relevant information, then you can create custom fields on all of the previous entities, including on Test Steps and also on Test Runs, if you wish to do so.

C	Bookstore / BO	_{ок-23} rs car	add books	to their she	opping bas	sket									
	Edit Q Commer	it As	sign More 🗸	Start Progress	Resolve Issue	Workflow 🗸	Admin 🗸								
~	Details Type: Priority: Affects Version/s: Component/s: Labels: Test Repository Path:	 Test Trivi None None defaul Shoppi 	al t ng Basket			Status: Resolu Fix Ver	tion: sion/s:	OPEN Unresc 1.0	(View Workflow) Ived						
>	Description														
	Test Details Type: Scenario Type: Scenario:	Cucum Scenar Given When J And I Then t	ber io I am on a proc select the si click the add the product is	duct detail pa ize/color/amou to basket but added to my s	ge nt ton hopping baske	t -	Add Field	Name*	Probability∫ Probability (Create	new field) Create	• field Cance	l S teps			
il 🚏	ira Dashboards 🗸 🛛	Projects 🗸	Issues 🖌 Boards	✓ Structure ✓ Xp	oorter Reports eaz	:yBl Tests 🗸 🔽	reate						Q Search) 1 . 4 [€]	0 C 🔘
8	Project setting	S				Create Test Du	n Field			_					
						Create Test Ru	n Field			- 1					
8 0) 4	Summary Details Audit log Re-index project		Test Run Cust Define Test Run "Ci Name	om Fields ustom fields" at proje	ct level Description	Name Description	hw temperatur	e		-		Flags		Actions	Create
2	Delete project					Туре	Number Field		~						
9 22 11	Issue types - Bug					Test Types Required	 This test run 	n field is req	v						
* * * * *	 - Pre-Condition - Story - Sub-bug - Sub-task - Sub Test Execution 								Create	Cancel					
	 Task Test Test Execution 2 more issue types 														

- Advantages of using Jira issue types in Test Management
- Configuring Test Step Custom Fields
- Configuring Test Run Custom Fields

Trace relationship between entities, up to the code

Xray provides full traceability between requirements, tests, their runs, and reported defects. This traceability not only provides the relation between the entities but also their status based on testing.

Traceability can be evaluated for a specific version and/or a specific environment, as its contents will depend on the testing results obtained for that specific context.

In the following screenshot, we can see an Epic that is NOK on version 1.0 even though one of the related Story issues is OK. In this example, the latest result for one of the tests (BOOK-23) that cover the Epic was a failure. It's also possible to see that a defect (BOOK-32) has been reported on that Test Run.

Traceability Report Switch report ~

🖞 Export 🖌

Showing 1 of 1 entries 0 🗸

Scope: Version; Version: 1.0; Environment: All Environments 🗸 👳 Contains text: BOOK-8 🗸 🜉 How to read this report

Requirement	Tests	Test Runs	Defects
BOOK-8 COZR 1.0 - NOK Version: 1.0 As a visitor, I can manage my Shopping Basket	 BOCK-24 OPEN Test visitors can remove books from their shopping basket 10-PASS 	PASS BOCK-31 Uvero Details Version: 1.0 Finished On:25/Feb/19 2:07 PM Executed By:xadmin Tests environments- Revision: Sed64ug/Tepr	
	BOOK-25 OPEN Test a visitor can view all the books in his shopping basket 10 -PASS	PASS BOOK-31 Uver Details Version: 10 Finished On:25/Feb/19 2:07 PM Executed By:xadmin Tests environments- Revision: Sed64ug/Rer	
	BOOK-23 OPEN Test visitors can add books to their shopping basket 1.0 -FAIL	PAL BOOK-31 C Vere Details Version: 1.0 Finished On:25(Feb/19 2:10 PM Executed By:xadmin Tests environments:- Revision:65664uyg7t6r	BOOK-32 CLOSED Error when adding Book to shopping basket
BOOK-11 RESOLVED 1.0 - OK Version: 1.0 As a visitor, I can view all the books in my shopping basket	BOOK-25 COETS Test a visitor can view all the books in his shopping basket 10 -FASS	CRSS CONC-31 CVersion: 1.0 Finished On:25/Feb/19.2:07 PM Executed Byxadmin Tests environments	

This helps auditing and diagnosing, knowing exactly what is impacting on what.

In Jira we can even look at the code of the requirements (e.g., Epic or Story issues) to facilitate analysis. The same can also be applied to automated tests that will have a corresponding Test issue that we can reference on the code commits. This helps analyze if a potential reported bug is on the features or even on the test automation code.

14: 2 pull requests						0 Start v	vatching this issue
ID	Title	Status	Author	Reviewer	Updated	11/Mar/21 7:44 PM	
#4149		MERGED		r 12 1	3 days ago	49 minute	sago
#4136	Feature/) = 17314	MERGED		R° R° 33	4 days ago	3	0
							Om
							1w 2d 4h 43m
							Updated 3 days ago
							Latest 3 days ago
						S MERGED	Updated 3 days ago Latest Yesterday

- Development
 - 2 branches
 - 9 commits
 - 2 pull requests MERGED

Facilitated diagnosis and Root-Cause Analysis

Root Cause Analysis (RCA) involves answering questions like these:

Updated 3 days ago Latest 3 days ago Updated 3 days ago

- What is the root cause of a problem?
- When was a problem introduced?
- Why was the problem introduced?
- Where was the problem introduced at?
- How can it be prevented to happen in the future?

Xray helps answer these questions in multiple ways, using all the capabilities mentioned earlier.

To find when a problem was introduced, for example, we can look at coverage information which can be used to identify the status of the requirement on each version. We can then use the Traceability Report or the Test Runs List Report to see in which revision it was reported, comments and other testing evidence left.

Learn more:

• [Xray] Xray's features for handling Root Cause Analysis

Learning

Facilitated training resources to improve knowledge and ensure a seamless adoption

Understanding a tool, how it works, its recommend use, possible configurations and extensions/integrations is essential to make the most out of it and fine tune it to the team and overall process needs.

Besides the extensive user guide documentation available online, there are also many courses on Xray Academy to understand not only Xray essentials but also more specific/advanced topics, such as test automation.

Learn more:

- Xray Academy
- Xray server/datacenter user guide

Standards and regulatory requirements

Standards and regulation that apply to organizations depend on the sector(s) they are working at and the type of products being developed and maintained.

For Medical Device Regulation (MDR), for example, these are some of the potential standards to consider:

- ISO 13485
- IEC 62304:2006
- ISO 14791:2019
- US FDA CFR Part 11