# How to collect information and organize it during test sessions

#### Warning: Content Compatibility Notice

Please note that the articles in this documentation feature media from app version 2.0.5. Interface elements may differ in newer versions. Refer to the latest app version for the most accurate information.

- Overview
- Findings and evidence
- Text notes
  - Evidence and audio recordings
- Tips for collecting and organizing information
- Text notes
  - Assess the different categories you want to have to mark information
  - Organize text notes using mindmaps
  - Focus on the problem and not on the individual
  - Screenshots
    - Use visual annotations to highlight relevant areas to make explanations clearer
    - Combine screenshots with categorized notes
    - Record only what matters
  - Video/screen recordings
    - Record only what matters
  - Audio recordings
    - Use audio notes
      - Combine screen recordings with audio notes
  - Evidence
    - Upload evidence and add categorized notes to provide better context
    - If using the browser, record the traffic to a .har file
  - General
    - Sequence matters, so record it
- References

## Overview

While performing the test sessions, testers collect and organize information so they can share it with the stakeholders or with the internal team.

In this article, we'll cover the essentials of collecting data that can be turned into actionable information, so that we can improve the product or system we're building.

# Findings and evidence

To share findings & evidence properly, we need to think about our goal: why are we doing it?

- · To ease the replication of a certain situation or bug
- To make RCA (Root-Cause Analysis) easier, and get to the source of the problem

Perhaps we're collecting information for ourselves, or maybe we're thinking about reporting defects so the developers can have a look at them. Maybe we have an idea to share with the PO or with the team for further discussion. Maybe something really works well, and the team needs to know that. Knowing to whom we're collecting information is relevant as we may need tailored information for them.

Let's see a brief summary of information that we can collect during exploratory testing and how it can be organized.

#### Text notes

Notes in the form of text are the most common way of storing our findings. These notes can be of different natures.

Testers use labels, or categories to distinguish text notes, to make them easier to find afterward.

Next are some examples of possible labels/categories that are frequently used, along with their meaning:

- Concern
- Something that represents a potential, negative risk that can somehow affect value, now, or in the future.
- Problem
- A clear problem that impacts value to some stakeholders (internal or external).
- Question

   Something that is not clear; may or not affect value.
- Suggestion
  - A recommendation/suggestion to change some existing aspect/feature.
- Idea
  - Some ideas to make the product better and thus improve it, usually by recommending new features. Eventually, you may merge "Suggestion" with "Idea."
- Praise/Positive
  - Some positive aspects we have found and that we want to share with the stakeholders, usually the internal team.
- Comment
  - A general note/comment.

## Evidence and audio recordings

The evidence consists mainly of files that we either extract from the application (e.g., logs, other artifacts) or that are strongly connected to the system (e. g., screenshots, videos).

Audio recordings, usually taken more as a verbalized text note, can also be included in this section as they will be stored as a file that we can upload as evidence.

Evidence is like facts that are of great help later on, for example, for bug analysis and fixing.

In sum, we can have the following:

- screenshots
- video/screen recordings
- audio recordings
- logs
  - application logs
  - JS console logs
  - crash dumps
     ...

# Tips for collecting and organizing information

#### Text notes

#### Assess the different categories you want to have to mark information

Start with a few categories (e.g., Problem, Question, Idea, Praise) and adapt to your needs.

XEA supports taking text notes using these note types: Comment, Problem, Suggestion, Idea, Question, Concern, and Positive.

🔍 🔍 🔍 Xray Ex	ploratory App	• Jira: xra	ytutorials.atla	ssian.net
Test	Timeline		Minir	nize []
	Webce	enne Page elet. Ner en orc'anal.		
TAKE A NOTE				
Comment		<b>\</b> ~   :≡	• +•	
Problem				
Suggestion	1			
Idea				
Concern				
Positive				- 11
Comment	~		c	lear
		liscard	Save	
_				
Scre	enshot	) [0	Record vide	0
Take	a note	] 💽	Record audi	0
Pause	session	0	End sessior	
🗲 Xray		used time 44:15	R (	emaining time 00:00:00

#### Organize text notes using mindmaps

- some users prefer a more visual and hierarchical way of organizing findings; mindmaps may work well, either using tools such as Miro, Mindmup, Xmind, or even the free Freemind tool
- mindmaps allow a totally flexible yet non-standard way to organize way notes; this may create some challenges in navigating through different test session results and even searching for what matters in a given session •



In the end, add the mindmap or a link to it, as evidence or as a note in your test session.


#### Focus on the problem and not on the individual


Whenever taking text notes, avoid mentioning someone as the cause of the problem. Focus instead on technical facts/evidence. It's ok to mention some decisions that may have been taken in the past as it can be connected to the problem and may also point to other related impacts.

#### Screenshots

#### Use visual annotations to highlight relevant areas to make explanations clearer

Screenshots are quite valuable as they make information visible, which would be hard to put into words. However, we often want to refer to a certain part of the application/site. By drawing around what we want, we can make it clearer for review later on.





## Combine screenshots with categorized notes

Take a screenshot and add some text, marking it as a Problem, Idea, or other. This will provide more context to the screenshot you're taking.

In the app, this is done at the same time you take the screenshot, right after the screenshot, at the bottom.


•••			Xray E	xplorato	ry App			
5	2	×	2	1	۰ LS		Тт	t <u>,</u>
⇒ C A NotSecure	robotwebdene Nerskuepp can	(weicome.Net)						te a power outlet.
			Welcome	Page				
			Login succeeded. No	v you can <u>ioppul</u> .				
							_	
Aa∽	BI ·			i≡ ¢	'⊜⊞	<b>"</b>	0 -	
page see	ins to be quit	e empty	r1					
Comment Concern								
Controllin	·							Clear
Add Is	sue	Add Defe	ect			Discard		Save

## Record only what matters

4

To provide greater focus and avoid some noise, record just the browser, or the application's UI. Record the whole screen if it makes more sense for your use case (e.g., the interaction of a desktop application with other applications).

In the Xray Exploratory App, the selection of what to record (i.e., the desktop, a specific application) whenever performing video recordings, or screenshots, is done at the start of the testing session. It can also be performed after resuming a paused session.




## Video/screen recordings

#### **Record only what matters**

To provide greater focus and avoid some noise, record just the browser, or the application's UI. Record the whole screen if it makes more sense for your use case (e.g., the interaction of a desktop application with other applications).

# 4


In the app, the selection of what to record (i.e., the desktop, a specific application) whenever performing video recordings, or screenshots, is done at the start of the testing session. It can also be performed after resuming a paused session.



## Audio recordings

#### Use audio notes


If you prefer to verbalize while testing, then record audio notes and review them later.



#### Combine screen recordings with audio notes

Combine screen recording with audio notes, so you can stay even more focused on testing.

In the app's global settings, you can enable "Audio on screen capture."



## Evidence

## Upload evidence and add categorized notes to provide better context

Upload some files as evidence and add some text, marking it as a Problem, Idea, or other. This will provide more context to the screenshot you're taking.

This is done at the same time you upload evidence, at the bottom.

• • •		Xray Explo	oratory App		
	Stor	e -Test Plan	Advanced Q	R	
	(4).0				
Aa~ E	I   A	V   := :=	୧ ଓ 🖪		
		tion. Shouldn't it b			
Comment Type					
					Clear
Question	~				
Question Add Issue	Add De	fect		Discard	Save

## If using the browser, record the traffic to a .har file


Record the browser network traffic and upload it to XEA. In Chrome, this can be found in "Developer Tools > Network"; make sure to select "Preserve Log" option.

Later on, the .har file can be uploaded from the same place to be analyzed in further detail.

🕞 📔 🛛 Elements C	onsole Recorder 🛦 Perf	ormance insights 👗	Sources Network	Performance		📁 2   🏟 🚦 🗄
🔍 🛇   🔽 ୧   🗹 ୮	Preserve log 📔 🔲 Disable cache	No throttling 🔻 🤶	⊊ <u>≜</u> <u>±</u>			1
5000 ms	10000 ms 15	5000 ms 20	0000 ms 25000 Export HAR		30000 ms	35000 ms
		<u> </u>		·	<u>+</u>	
Name	Status	Turce	Initiator	Size	T Waterfall	
	(canceled)	Type xhr	minator	O B		
	200	fetch		152 B		
─ ○ ?action=reportMetrics	200	fetch		1.1 kB	5. •	
?action=reportMetrics	200	fetch		894 B	5. 📲	
I feed/	200	document	Other	120 kB	1. 💶	
radar.html	302	document / Redirect		(disk cache)	1.4	
radar.html?customer-i	200	document	radar.cedexis.com/1/1	(disk cache)	8. 4	
providers.json?image	200	xhr	radar.cedexis.com/16	1.1 kB	2. 1	
☐ track	(unknown)	fetch		0 B	(	

blocked URL

Add the .har file as standard evidence to your test session. Switch to the "Timeline" view and then drag the file to XEA.



## General

#### Sequence matters, so record it

Problems often occur due to having the target system/application in a certain state, which in turn is the consequence of a sequence of steps. To replicate problems/situations, we need to remember the sequence of actions performed.

# 4

The Xray Exploratory App produces a timeline with the notes and evidence you take. This timeline will be available as a . PDF report. It's also possible to perform a desktop/application screen recording to make it more trustworthy and easier.

# References

- PQIP
  - Three Digestible Diagrams to Describe Exploratory Testing